

# mobiTALK

## PTT Button Configuration and Functionality

*Updated: September 2023*

# Introduction

This document is intended as a helping guide on how to take full advantage of the PTT physical button integration, that mobiTALK offers on the following supported phones:



[Sonim XP8](#)



[Samsung Xcover Pro 2](#)



[Samsung Galaxy Xcover 4](#)



[Ulephone Armor X5](#)




## mobiTALK with Sonim XP8

### SUPPORTED FEATURES

With mobiTALK on-screen	With mobiTALK off-screen (or locked screen)
<ul style="list-style-type: none"> <li>- PTT Button Short press to toggle Mic ON/OFF</li> <li>- PTT Button Press and Hold to Talk</li> </ul>	<ul style="list-style-type: none"> <li>- PTT Button Short press to toggle Mic ON/OFF</li> <li>- PTT Button Press and Hold to Talk</li> </ul>


### CONFIGURATION



1. First you'll need to switch *Battery Optimization*, by going to the *Battery Usage* settings of mobiTALK.
2. Within this screen tap *Battery Usage*.



3. Select All apps on the dropdown menu and find mobiTALK.
4. Select *Don't Optimise* and tap *Done*.



5. Now go to the system *Settings*.
6. Tap the option *Programmable Keys*.
7. Tap *Select PTT Key App*.
8. Search mobiTALK and tap to select.




## mobiTALK with Samsung Xcover Pro 2


### SUPPORTED FEATURES

With mobiTALK on-screen	With mobiTALK off-screen (or locked screen)
<ul style="list-style-type: none"> <li>- PTT Button Short press to toggle Mic ON/OFF</li> <li>- PTT Button Press and Hold to Talk</li> </ul>	<ul style="list-style-type: none"> <li>- PTT Button Short press to toggle Mic ON/OFF</li> <li>- PTT Button Press and Hold to Talk</li> </ul>

### CONFIGURATION



1. Go to the general system *Settings* and tap *Advanced Features*
2. Tap *Xcover Key*.
3. Switch ON the option *Use Xcover Key with App*.
4. Tap the box with the *Use Xcover Key with App*.
5. Select *mobiTALK*.



6. Go back to the main *Settings* screen and tap *Apps*
7. Find *mobiTALK* and tap to enter the *App Info* screen
8. Within this screen tap *Battery*
9. Select *Unrestricted*.



## mobiTALK with Samsung Galaxy Xcover 4

### SUPPORTED FEATURES

With mobiTALK on-screen	With mobiTALK off-screen (or locked screen)
<ul style="list-style-type: none"><li>- PTT Button Short press to toggle Mic ON/OFF</li><li>- PTT Button Press and Hold to Talk</li></ul>	<i>(None)</i>

### CONFIGURATION

*No configuration needed, works as is when mobiTALK is on the foreground*

---



## mobiTALK with Ulephone Armor X5

### SUPPORTED FEATURES

With mobiTALK on-screen	With mobiTALK off-screen (or locked screen)
<ul style="list-style-type: none"><li>- PTT Button Short press to toggle Mic ON/OFF</li><li>- PTT Button Press and Hold to Talk</li></ul>	<i>(None)</i>

### CONFIGURATION

*No configuration needed, works as is when mobiTALK is on the foreground*

---



# Troubleshooting

Symptom	Action(s)
The PTT icon might not be displayed on the groups/1:1 conversations, when the app is installed/updated.	Navigate to the settings tab from the profile or manually publish in a group, will make the PTT option appear
Leaving the phone in the background overnight can lead to connection issues. Thus causing PTT to behave erratically.	Clearing the data and logging in again can resolve any connectivity problems
Clearing the app from recents apps will affect the PTT functions	App should remain running completely in the background

## Support

If you have any questions or would like support with this process please contact your Mobilus rep or Robert Hamilton at [info@mobiluslabs.com](mailto:info@mobiluslabs.com)

